

Temp

The Animation Tab is shown below. This provides the various adjustments and parameters to control animation of objects.

The screenshot displays the 'Animation' tab of the software interface. It features a dark-themed layout with several sections for controlling object animation. Each section has a checked checkbox, a set of input fields, and an 'add modifier' or 'add filter' button. The sections are: Pan (%), Zoom (%), Rotate, Center, Framing, Opacity, Blur, and Color correction. At the bottom, there is a 'Key frame time' field with a value of 0 and a unit of ms.

Property	Value	Action
Pan (%)	X: 0, Y: 0, Z: 0	add modifier
Zoom (%)	X: 90, Y: 90, 100%	add modifier
Rotate	C: 0, Y: 0, X: 0	add modifier
Center	X: 0, Y: 0	add modifier
Framing	S: 100, X: 100, Y: 0	add modifier
Opacity	A: 100	add modifier
Blur	R: 0	add modifier
Color correction		add filter
Key frame time	0 ms	


- For Pan and Rotate, adjustments can be made in three planes
 - X,Y and Z for Pan
 - C,Y and X for Rotate
- These adjustments replace the 3D parameters provided in Version 8.
- A new adjustment called Framing is provided (see [Framing](#))
- The Color Correction parameters have been expanded in Version 9 ([Color Correction](#))
- The “Key Frame Time” box shows the time (in milliseconds) of the selected Key Frame

Parameter Controls

Display Mode for Pan and Zoom


Click on the “%” sign or the “100%” sign:

- “%” = Percentage Mode
- “px” = Pixels Mode
- “pt” = Original Points Mode
- “100%” = Full Height of Project Screen
- “Original Pixels” = The Original Pixel Size of the Image




The Illustration below shows a 640×480 rectangle at Original Size in a 1920×1080 Project


- In Percentage Mode:
- The values for “X” and “Y” Pan are calculated for the Centre of the Object/Rectangle with respect to the Centre of the Slide
- The value of the Zoom Parameter is the percentage of the Full Height of the Project Screen (in this case 1080 pixels)
- $480/1080 = 0.444444444444 = 44.44444444\%$



- In Pixels Mode:
- The values for "X" and "Y" Pan are calculated for the Top Left Corner of the Object/Rectangle with respect to the Top Left Corner of the Slide
- The value of the Zoom Parameter is the Pixel Size of the Object/Rectangle




- In Points Mode




The Centre Control

- The "CENTRE" Control can be used to move the CENTRE or "Point of Rotation" of an Object as shown below:




The Rotate Control


- The “Rotate C” Control will rotate an Object about its Centre Point in the same plane as the screen:




- The “Rotate Y” Control will rotate an Object about its Centre Point in 3 Dimensions Horizontally:



- The “Rotate X” Control will rotate an Object about its Centre Point in 3 Dimensions Vertically:



- The "C", "Y" and "X" Rotate Controls can be used simultaneously:



Changing Parameters with the Mouse

- Place the Mouse on any Letter (e.g. X,Y or Z in the Pan Controls) and click and drag left or Right
- You can also Right Click on any Letter and access commonly used Preset Values (See Right Click Menus below)

- You can “double click” on any letter to change the value back to its default state

Keyboard Entry

- In any box, highlight the existing value and type in a new value

OR Place the cursor in a box and:

- UP arrow on Keyboard increases the value by one unit
- DOWN arrow decreases the value by one unit
- Pg Up on Keyboard increases the value by ten units
- Pg Dn on Keyboard decreases the value by ten units

The UNITS depend on the chosen Display Mode:

- In % Mode the units will increase/decrease by 1% or 10% of the Parent Frame (or Background)
- In Px Mode the units will increase/decrease by 1 Pixel or 10 Pixels - relative to Project Size
- In Pt Mode the units will increase/decrease by 1 Pixel or 10 Pixels relative to the Original size of the Object

Pan

- The parameters can be read in Percentage, Pixels or Original Points
- X - Horizontal movement of the Object relative to the width of the Object's Parent Frame
- Y - Vertical movement of the Object relative to the height of the Object's Parent Frame
- Z - Zoom - “Closer to” or “further away from” the viewer

Zoom

- The parameters can be read in Percentage, Pixels or Original Points
- X - The horizontal dimension relative to the native size/resolution of the Object's Parent Frame
- Y - The vertical dimension relative to the native size/resolution of the Object's Parent Frame
- With the “Chain Link” deselected the object can be distorted
- With the “Chain Link” restored the distorted image/object can be scaled
- Click on 100% to return to default settings (100%)


The UNITS depend on the chosen Display Mode:

- In % Mode 100% = 100% of the Parent (Slide / Frame etc)
- In Px Mode the Pixel Dimensions of the Object are shown
- In Pt Mode 100% = 100% of the Native Pixels of the Object


Framing

- Framing can be used to Pan and/or Zoom an Image within a Frame without modifying the frame itself
- Framing can also be used to adjust an Aspect Ratio mismatch
- In the example below a 4:3 image is shown within a 3:2 frame at 90% of full screen in a 16:9 Project.

- In the default 100% Scaling (S) the 4:3 Image has been “cut off” at the top and bottom of the Image and “Fits” the Width of the 3:2 Frame.




- By adjusting the “S”, “X” and “Y” Controls a “Best Fit” composition can be achieved
- Further Panning and Zooming is possible




Opacity and Blur

- The Illustration shows Main Image used as a Background Image at 100% Opacity and Zero Blur



- The following Illustration shows the same Background Image with reduced Opacity and a little Blur



Modifiers

- Modifiers can be applied to an Animation of an Object / Image between two Key Frames
- The Modifier is applied to the first Key Frame of a pair of Key Frames defining the animation
- Click on “Modifier”

The screenshot shows the Modifiers panel with the following settings:

- Pan (%)**: X: 0, Y: 0, Z: 0. The 'add modifier' button is highlighted with a red box.
- Zoom (%)**: X: 100, Y: 100, Link icon, 100%. 'add modifier' button.
- Rotate**: C: 0, Y: 0, X: 0. 'add modifier' button.
- Center**: X: 0, Y: 0. 'add modifier' button.
- Framing**: S: 100, X: 0, Y: 0. 'add modifier' button.
- Opacity**: A: 100. 'add modifier' button.
- Blur**: R: 0. 'add modifier' button.

- The drop-down shows a number of options, the first being Animation Speed

Animation speed	
Pan.X	>
Pan.Y	>
Pan.Z	>

- Accelerate
- Slow down
- Smooth
- Custom

- Acceleration - the animation starts “slowly” and builds up to a maximum
- Slow Down - the animation starts at maximum speed and finishes smoothly
- Smooth - Starts and ends smoothly, with the maximum speed in the middle
- Custom - Linear Acceleration to the Middle of the animation and Linear Deceleration to the finish - a starting point for a Custom Setting

▼ Animation speed: Accelerate

Accel. time (%)

56

Decel. time (%)

1

Start speed

0

Final speed

0

▼ Animation speed: Slow down

Accel. time (%)

1

Decel. time (%)

56

Start speed

0

Final speed

0

▼ Animation speed: Smooth

Accel. time (%)

26

Decel. time (%)

26

Start speed

0

Final speed

0

▼ Animation speed

Accel. time (%)

50

Decel. time (%)

50

Start speed

0

Final speed

0

- Pan, Zoom, Rotate etc all have a set of modifiers labelled:
 - Oscillation
 - Jumping
 - Ping Pong
 - Shift

Animation speed	>	
Pan.X	>	Oscillation
Pan.Y	>	Jumping
Pan.Z	>	Ping pong
		Shift


- The following Video demonstrates the various Modifiers



Video

Colour Correction

- Click on “Add Filter” to display a list of available Colour Correction Adjustments:




The available Adjustments are:

- Levels
- Brightness / Contrast
- Hue / Saturation
- Toning
- Colouration
- Negative

Levels


- The Adjustments:



- Click and drag within the area outlined to the Left and / or Right to change the value of the adjustment
- Values can be entered directly via the keyboard
- Increasing the Black Point and decreasing the White Point will apply Contrast to the Object / Image
- Increasing / Decreasing the Midtones will Lighten / Darken the Object / Image

Brightness / Contrast


- The Adjustments:



- Click and drag within the area outlined to the Left and / or Right to change the value of the adjustment
- Values can be entered directly via the keyboard
- Drag to the Left / Right to Decrease / Increase Brightness
- Drag to the Left / Right to Decrease / Increase Contrast

Hue / Saturation

- The Adjustments:




- Click and drag within the area outlined to the Left and / or Right to change the value of the

adjustment

- Values can be entered directly via the keyboard
- Drag to the Left / Right to change the Hue
- Drag to the Left / Right to Desaturate / Saturate the Object / Image
- Drag to the Left / Right to Darken / Lighten the Object / Image

Toning

- The Adjustments:
- Choose from Grayscale, Sepia or Cyan



- Click and drag within the area outlined to the Left and / or Right to change the value of the adjustment
- Values can be entered directly via the keyboard
- Click on the Colour /Grayscale to open the Choose Colour Box and change the Tone
- Drag the Amount Slider to the Left to Decrease the Effect

Colouration

- The Adjustments:
- Choose from Red, Green or Blue



- Click and drag within the area outlined to the Left and / or Right to change the value of the adjustment
- Values can be entered directly via the keyboard
- Click on the Colour to open the Choose Colour Box and change the Tone
- Drag the Amount Slider to the Left to Decrease the Effect


Negative

- No Adjustments
- Creates a Negative version of the Object / Image
- Combine with Grayscale Toning or Desaturation to make a Black and White Negative from a Colour Image



Key-frame Time

- Allows for precise positioning of Key-Frames



From:

<https://docs.ptavstudio.com/> - PTE AV Studio

Permanent link:

<https://docs.ptavstudio.com/en-us/11.0/temp?rev=1574634143>

Last update: 2022/12/18 11:20

